Как да използвам Bootice

- 1. Изтеглете Bootice и разопаковайте RAR архива.
- Отворете*BOOTICEx86_2016.06.17_v1.3.4.0.exe*(за 32-битов Windows) или*BOOTICEx64_2016.06.17_v1.3.4.0.exe*(за 64-битов Windows), в зависимост от вашия <u>Тип архитектура на ОС</u>.
- 3. Ако бъдете подканени от UAC, щракнете върхуДа.
- 4. За да архивирате MBR, отидете на *Обработка на MBR*> *Резервно MBR*, задайте резервен файл и обхват на сектора, след което щракнете *Архивиране*.

Physical disk Disk image BCD Utilitie Description	Master Boot Record	×					
MBR or PBR of your disks. In addition, BOOTICE offers you the pos to edit disk sectors, to backup or restore format disks.	Available MBR Types WEE (wee63.mbr) A mini version of grub_for_dos, it can be track of the hard drive. (62 sectors)	installed on the MBR					
Destination Disk	GRUB4DOS 0.4.5c/0.4.6a (grldr.mbr)	ed on CNU CRUR (16					
HD1: TOSHIBA DT01ACA200 (1.8	sectors)	eu un divo dicos.(10					
Refresh Process MBR Process PBR	GRUB 2.00 (boot.img + core.img) A powerful universal boot manager from biodisk part modes fat exfat exf2	Sectors backup	×				
http://www.ipauly.com	C Lvyanan 1JF9z A boot manager by Lvyanan. It support	C:\Users\elnco\Desktop\WindowsReport.bin					
	Dies Bast Massac 5 0 45 Test	Sectors to backup					
	A boot manager with cool UII Boot your floppy/cdrom/usb without BIOS support	start sector: 0 < > sectors: 1 - +					
	UltralSO USB-HDD+ / USB-ZIP+	Total sectors: 3907029168, sectors to backup must be less that	n 3907029168.				
	Enhanced USB-HDD / USB-ZIP boot prog compatibility.(1 sector)	Bada	up Cancel				
	O Windows NT 5.x / 6.x MBR Boot form the 1st active primary partition	n.(1 sector)					
	Current MBR. Type: UltralSC	D USB-HDD+					
	Install / Config Backup MBR Re	store MBR Close					

5. За да промените MBR, отидете на*Обработете MBR*, изберете типа MBR и натиснете*Инсталиране / конфигуриране*.



6. За да възстановите MBR, отидете на *Обработка на MBR*> Възстановяване на MBR, задайте файла за възстановяване и обхвата на сектора, след което щракнете *Възстанови*.

	Master Boot Record X							
BOOTICE v1.3.4 x64 - by P	Available MBR Types WEE (wee63.mbr) A mini version of grub_for_dos, it can be installed on the MBR track of the hard drive. (62 sectors)							
Physical disk Disk image BCI	GRUB4DOS 0.4.5c/0.4.6a (grldr.mbr)							
Description BOOTICE is a portable utility MBR or PBR of your disks. In addition, BOOTICE offers to edit disk sectors, to back	Sectors restore X Restore file D:\WindowsReport MBR backup.bin							
Destination Disk	File size: 1339229830 Bytes (2615684 sectors).							
HD1: TOSHIBA DT01AC	Sectors to restore							
Refresh Process MBR	start sector: 0 <							
http://www.ipauly.com	Restore Cancel							
	Boot form the 1st active primary partition.(1 sector)							
	Current MBR Type: UltraiSO USB-HDD+							
	Install / Config Backup MBR Restore MBR Close							

7. За да архивирате, промените или възстановите PBR, следвайте същите стъпки, както погоре, но за*Обработвайте PBR*.

						Partition Boot Record			
						Destination Partition			
						GPT1: (NTFS, 1.8 TB, D: Things) ~			
👂 воотісе	v1.3.4 x64 -	by Pauly				Available PBR Types			
Physical disk	Disk image	BCD U	tilities	UEFI	Command	MS-DOS boot record (FAT/FAT32) Boots up Win9x or MS-DOS by loading IO,SYS, (0 secs)			
Description									
BOOTICE	s a portable u	tility to man	ipulate	(install,	backup, res	GRUB4DOS 0.4.5c/0.4.6a (FAT/FAT32/NTFS/ExFAT)			
In addition, BOOTICE offers you the possibility to manage disk				aity to r	Grub4Dos on partition, loads GRLDR from the root of this partition. (4 secs)				
to edit dis	sectors, to b	ackup or re	store di	sk secto	ors, to partiti				
format disks.				Windows 2000/XP/2003 boot record, It loads NTLDR					
Destination Disk					from the root directory. (8 secs)				
HD1: TO	SHIBA DT01	ACA200 (1.8 TB	, D:)		BOOTMGR boot record (FAT/FAT32/NTFS/ExFAT)			
Defrech	Dracare MPD	Dragage	000	Darks	Manage	Windows Vista/7/8 boot record. It loads BOOTMGR (NTLDR first on NTES) from the root dir. (12 secs)			
Refresh	Process MDR	Process	PDR	Parts	Manage				
						SYSLINUX 5.10/6.03 (FAT/FAT32/NTFS) SYSLINUX is a boot loader for Linux systems which runs			
ttp://www.ipauly.com					on an FAT filesystem. (1 secs)				
						FreeDOS (FAT/FAT32)			
						FreeDOS boot sector (Search and load Kernel.sys in the root directory). (0 secs)			
						Current PBR Type: KBOOTMGR boot record			
						Install / Config Backup PBR Restore PBR Close			

8. За да управлявате дялове, натиснете Управление на части, изберете обем на диска и изберете предпочитана опция (напр. Форматирайте тази част, Преразделяне, Резервна таблица на дялове).

	Partitio	n Management							
BOOTICE v1.3.4 x64 - by Pauly -	No.	Vol. Label	Drive	Type	Hid.	FileSvs. S	tart LBA	Total Sectors	Capacity
Physical disk Disk image BCD Utilities UEFI Command	line o	No. of Contraction	78367	MS Reserved	10000	-	34	32734	16.0 MB
Description BOOTICE is a portable utility to manipulate (install, backup, res MBR or PBR of your disks. In addition, BOOTICE offers you the possibility to manage disk	tor Dai	Things		Basic Data		NTES	32768 3906994176		1.8 TB
to edit disk sectors, to backup or restore disk sectors, to partit format disks.	n								
HD1: TOSHIBA DT01ACA200 (1.8 TB)									
Refresh Process MBR Process PBR Parts Manage	Se [Curr [Part	ent Disk]: HD 1 itioning sheme]:	TOSHIBA	DT01ACA200 (1 [C/H/S]: 24320	. <mark>8 TB)</mark> 1/255/63	3; [Total Sectors]: 39(07029168/5	12; [Capacity]	: 1.8 TB.
ttp://www.ipauly.com	Opera	ation							
		Activate	Hide	Unhide	Assi	ign Drive Letter	Remove D	rive Letter	Spt attribute
					-				a state of the second stat